

UR1973.65

Computer programmes for metric conversion.

E.L. Martin

A comprehensive programme (9A1; V = 5917) enables rapid conversion of data and the production of various types of conversion tables.

Abbreviations and definitions

CF = conversion factor
 Input number = number to be converted
 Output number = converted numbers
 SF = special function key
 SReg = storage register

DATA CONVERSION

Provides simple numerical conversion with print-out of input and output number. Both input and output numbers are automatically totalled. The totals can be recalled at any time (SReg 08 and 09 respectively) and may also be printed. The print-out format may be adjusted (refer to Table 1).

Operation

- (1) Key CF, SReg 00
- (2) PRIME, GO
- (3) Key input number, GO

To continue, repeat (3).

To print totals, key SEARCH +. If you wish to leave a line space above and, or below the total, then key SF 15 before and, or after SEARCH +.

If the input number is not an integer programme steps 015 and 032 must be altered to give the required number of decimal places.

The programme may be altered to accept an input number consisting of two units (e.g. feet and inches):

Step	Existing Code	Alter to
011	0514	0301
014	0411	0514 (GO)
015	0900	0514 (GO)
016	0604	0514 (GO)
031	0411	0300
032	0900	0514 (GO)

The mode of operation will then be:

- (1) Key CF, SReg 00
- (2) Key number of smaller input units equal to larger input unit, SReg 15
- (3) PRIME, GO
- (4) Key larger unit input number, GO
- (5) Key smaller unit input number, GO

To continue, repeat (4) and (5).
 To print totals, key SEARCH +.

Table 1. *FORMAT CONTROL: PROGRAMME STEP NUMBERS, CODES AND VALUES FOR PROGRAMME 9A1.*

Programme	Input Number			Output Number			Column Spacing			
	1 unit	2-unit		1 unit	2-unit		Initial	1/2	2/3	3/4
<i>Step</i>										
9A1 (1)	015	584	590	263†	627	637	-	-	-	-
Totals	032	603	613	036	627	637	-	-	-	-
9A1 (2) *	268	-	-	263†	627	637	199	051	058	065
9A1 (3) *	421	-	-	263†	627	637	199	098	110	122
9A1 (4) *	-	303	307	263†	627	637	199	156	164	172
		333	337							
		363	367							
		393	397							
<i>Code</i>										
	0900	0600	0200	0902	0600	0200	1509	1505	1505	1505
<i>Value*</i>										
	10	7	3	13	7	3	9	5	5	5

*The sum of the values of the input and output numbers must not exceed 24, otherwise the column spacing must be reduced to keep the table within the width of the paper.

†Programme step 244 must also be altered if step 263 is changed. The numerical value represented by the code for step 244 should equal the last digit of the code for step 263.

The programme may also be altered to provide a two-unit output:

<i>Step</i>	<i>Existing Code</i>	<i>Alter to</i>
021	0200	0302
035	0411	0302
036	0902	0514 (GO)

The type of input determines the mode of operation. The number of smaller output units which equal the larger output unit is placed in SReg 25.

PRODUCTION OF CONVERSION TABLES

The format of these tables consists of four columns, and normally fifty rows (*i.e.* 200 increments). This standard will fit lengthwise on A4 paper.

For single unit input number proceed as follows:

Operation

- (1) Key CF, SReg 00
- (2) Key SEARCH, STORE DIRECT
- (3) Key SEARCH 2 (or SEARCH 3 if you wish the output number to be printed *before* the input number.)
- (4) The programme stops to enable you to type in a title for the table.
- (5) Key GO. Print-out commences and will be complete in about 5 minutes.

To continue key SF 05 and repeat operations (3) to (5).

The above operations give an increment of one. You may alter the increment by multiplication or division (or both).

To multiply: key factor required, SF 02

To divide: key factor required, SF 03

The starting number may be altered as desired. Key starting number required, less one increment, SF 01.

The above alterations must be performed immediately following operation (2).

If you do not require 50-row columns then operation (2) should be modified as follows.

- (2) Key number of rows required, SF 04

For 2-unit input number proceed as follows:

Operation

- (1) Key CF (for smaller unit), SReg 00
- (2) Key number of rows per column (this number must be exactly divisible by the number of smaller units which equal the larger unit), SF 04
- (3) Key SF 06, key number of rows per column, GO, key number of smaller units equal to the larger unit, GO
- (4) Key SEARCH 4

- (5) The programme stops to enable you to type in a title for the table
- (6) Key GO. Print-out commences and will be completed in about 5 minutes (for a column length of about 50).

To continue table key SF 05, SF 07 and repeat operations (4) to (6).

For 2-unit output number proceed as follows:

The programme must be altered as follows:

	Step	Existing Code	Alter to
(a) Single unit input	274	0200	0302
(b) Single unit input, reversed print-out	285	0200	0302
(c) Two-unit input	294	0200	0302

In all cases the number of smaller output units which equal the larger output unit must be stored: Key this number, SReg 25.

FORMAT CONTROL

The programme allows for an input number (integer) of nine digits and an output number of nine digits before the decimal point and two digits following the decimal point.

Where the programme is changed to allow for 2-unit numbers, these are formatted as follows:

Larger unit number : Six digit integer
Smaller unit number : Two digit integer

The programme can be modified to accommodate most input/output requirements. To modify the programme see Table 1, which lists the format control steps in the programme. Read the footnotes carefully to avoid a format which will exceed the width of the paper. If the format is within the width of the paper, but the right-hand margin of the table is too close to the right-hand edge of the paper the line feed mechanism may be rendered inoperative. The left hand margin setting of the typewriter is normally set at 10 but may be moved if required.

ROUNDING CONTROL

Two types of rounding control are used in the programme.

The first type is used for single unit output numbers. It must be adjusted if the programme step 263 is changed. The number entered as programme step 244 represents the number of decimal places. To round to the nearest integer this should be 0. It is also possible to round to the nearest 10, 100, 1000 etc.; in this case alter programme step 243 to CHANGE SIGN and enter in step 244 the number of digits, before the decimal place, plus 1, at which the rounding is to be applied.

The second type of rounding control does not normally need to be altered. It rounds the smaller unit of a 2-unit number to the nearest integer.

If decimal places of the smaller unit of the output number are required or if it is to be rounded to the nearest 10 or 100 the programme must be altered as follows:

<i>Number of decimal places</i>	<i>Programme alteration</i>	
	<i>Step</i>	<i>Alter to</i>
1	637	0712
	638	0700
2	636	0712
	638	0700
3	635	0712
	638	0700
<i>To the nearest</i>		
10	638	0700
100	638	0705
	639	0700

[revised 3 December 1973]

PROGRAMME 9A1 (v = 5917)

000	04 08	050	04 11	100	00 02	150	04 05	200	05 15
001	07 01	051	15 05	101	01 03	151	00 01	201	04 12
002	00 00	052	04 05	102	04 05	152	01 04	202	01 02
003	07 00	053	00 02	103	00 02	153	04 00	203	01 08
004	04 04	054	01 02	104	03 03	154	00 01	204	01 08
005	00 08	055	04 00	105	04 05	155	04 11	205	04 13
006	04 04	056	00 02	106	01 00	156	15 05	206	05 11
007	00 09	057	04 11	107	04 00	157	02 02	207	04 08
008	04 08	058	15 05	108	00 02	158	04 05	208	01 00
009	07 00	059	04 05	109	04 11	159	00 02	209	06 04
010	05 15	060	00 03	110	15 05	160	01 04	210	07 10
011	05 14	061	01 02	111	04 05	161	04 00	211	06 03
012	04 00	062	04 00	112	00 03	162	00 02	212	04 04
013	00 08	063	00 03	113	01 03	163	04 11	213	01 09
014	04 11	064	04 11	114	04 05	164	15 05	214	15 14
015	09 00	065	15 05	115	00 03	165	02 03	215	07 00
016	06 04	066	04 05	116	03 03	166	04 05	216	06 13
017	04 05	067	00 04	117	04 05	167	00 03	217	06 02
018	00 00	068	01 02	118	01 00	168	01 04	218	06 06
019	06 02	069	01 05	119	04 00	169	04 00	219	04 02
020	06 05	070	05 09	120	00 03	170	00 03	220	01 09
021	02 00	071	04 07	121	04 11	171	04 11	221	07 12
022	04 12	072	07 06	122	15 05	172	15 05	222	07 05
023	01 08	073	05 15	123	04 05	173	02 04	223	04 00
024	04 13	074	04 08	124	00 04	174	04 05	224	01 09
025	04 07	075	07 06	125	01 03	175	00 04	225	04 05
026	07 00	076	04 12	126	04 05	176	01 04	226	01 09
027	04 08	077	01 08	127	00 04	177	01 05	227	06 08
028	06 00	078	04 13	128	03 03	178	05 09	228	06 06
029	04 05	079	04 07	129	04 05	179	04 07	229	06 03
030	00 08	080	07 05	130	01 00	180	07 12	230	06 05
031	04 11	081	04 08	131	01 05	181	05 15	231	04 00
032	09 00	082	07 03	132	05 09	182	04 08	232	00 09
033	04 05	083	00 00	133	04 07	183	07 12	233	04 11
034	00 09	084	01 01	134	07 08	184	04 12	234	09 00
035	04 11	085	04 08	135	05 15	185	01 08	235	05 11
036	09 02	086	07 07	136	04 08	186	04 13	236	04 08
037	04 07	087	04 05	137	07 08	187	04 07	237	02 00
038	07 01	088	00 01	138	04 12	188	07 09	238	06 04
039	04 08	089	01 03	139	01 08	189	04 08	239	07 10
040	07 02	090	04 05	140	04 13	190	00 00	240	06 03
041	00 00	091	00 01	141	04 07	191	04 12	241	04 04
042	01 01	092	03 03	142	07 07	192	01 02	242	01 09
043	04 08	093	04 05	143	04 08	193	01 08	243	05 14
044	07 05	094	01 00	144	07 04	194	04 13	244	07 02
045	04 05	095	04 00	145	00 00	195	05 11	245	06 13
046	00 01	096	00 01	146	01 01	196	04 08	246	06 02
047	01 02	097	04 11	147	04 08	197	01 01	247	06 06
048	04 00	098	15 05	148	07 09	198	04 11	248	04 02
049	00 01	099	04 05	149	02 01	199	15 09	249	01 09

PROGRAMME 9A1 (continued)

250	07 12	300	04 05	350	04 00	400	01 04	450	04 04
251	07 05	301	02 01	351	02 02	401	04 05	451	01 07
252	04 00	302	04 11	352	07 00	402	01 04	452	07 01
253	01 09	303	06 00	353	04 04	403	06 04	453	04 04
254	04 05	304	04 05	354	01 02	404	04 05	454	00 01
255	01 09	305	01 01	355	04 08	405	00 07	455	04 04
256	06 08	306	04 11	356	06 12	406	05 09	456	01 00
257	06 06	307	02 00	357	05 11	407	04 07	457	04 00
258	06 03	308	07 01	358	04 08	408	06 14	458	00 02
259	06 05	309	04 00	359	02 03	409	07 01	459	04 00
260	04 00	310	01 01	360	04 05	410	04 00	460	00 03
261	00 09	311	04 05	361	02 03	411	02 04	461	04 00
262	04 11	312	01 01	362	04 11	412	07 00	462	00 04
263	09 02	313	06 04	363	06 00	413	04 04	463	04 00
264	05 11	314	04 05	364	04 05	414	01 04	464	00 05
265	04 08	315	00 07	365	01 03	415	04 08	465	05 15
266	01 02	316	05 09	366	04 11	416	06 14	466	04 08
267	04 11	317	04 07	367	02 00	417	05 11	467	00 05
268	09 00	318	06 11	368	07 01	418	04 08	468	04 05
269	06 04	319	07 01	369	04 00	419	03 03	469	01 07
270	04 05	320	04 00	370	01 03	420	04 11	470	04 00
271	00 00	321	02 01	371	04 05	421	09 00	471	00 01
272	06 02	322	07 00	372	01 03	422	05 11	472	04 00
273	06 05	323	04 04	373	06 04	423	04 08	473	00 02
274	02 00	324	01 01	374	04 05	424	04 04	474	04 00
275	04 05	325	04 08	375	00 07	425	07 05	475	00 03
276	01 00	326	06 11	376	05 09	426	07 00	476	04 00
277	05 11	327	05 11	377	04 07	427	04 08	477	00 04
278	04 08	328	04 08	378	06 13	428	00 04	478	04 05
279	01 03	329	02 02	379	07 01	429	04 04	479	01 08
280	06 04	330	04 05	380	04 00	430	00 02	480	04 00
281	04 05	331	02 02	381	02 03	431	04 04	481	00 05
282	00 00	332	04 11	382	07 00	432	00 04	482	05 15
283	06 02	333	06 00	383	04 04	433	06 04	483	04 08
284	06 05	334	04 05	384	01 03	434	07 02	484	00 01
285	02 00	335	01 02	385	04 08	435	06 02	485	04 00
286	05 11	336	04 11	386	06 13	436	04 14	486	00 01
287	04 08	337	02 00	387	05 11	437	00 03	487	04 00
288	01 04	338	07 01	388	04 08	438	06 02	488	00 02
289	06 04	339	04 00	389	02 04	439	06 05	489	04 00
290	04 05	340	01 02	390	04 05	440	04 04	490	00 03
291	00 00	341	04 05	391	02 04	441	00 05	491	04 00
292	06 02	342	01 02	392	04 11	442	04 04	492	00 04
293	06 05	343	06 04	393	06 00	443	01 08	493	04 00
294	02 00	344	04 05	394	04 05	444	04 05	494	00 05
295	04 05	345	00 07	395	01 04	445	00 03	495	05 15
296	01 00	346	05 09	396	04 11	446	04 00	496	05 14
297	05 11	347	04 07	397	02 00	447	00 04	497	04 08
298	04 08	348	06 12	398	07 01	448	04 05	498	00 02
299	02 01	349	07 01	399	04 00	449	00 04	499	04 02

PROGRAMME 9A1 (continued)

500	00 01	550	06 00	600	06 05	650	00 05
501	04 02	551	04 14	601	06 08	651	06 04
502	01 00	552	02 04	602	04 11	652	04 05
503	04 02	553	04 14	603	06 00	653	00 04
504	00 02	554	02 00	604	06 01	654	05 11
505	04 02	555	07 00	605	04 05	655	04 08
506	00 03	556	04 04	606	01 05	656	00 14
507	04 02	557	02 01	607	06 02	657	04 12
508	00 04	558	07 01	608	07 00	658	01 11
509	04 02	559	04 04	609	07 00	659	04 13
510	00 05	560	01 01	610	07 00	660	05 11
511	04 02	561	04 04	611	07 12	661	04 08
512	01 07	562	01 02	612	07 05	662	00 15
513	04 02	563	04 04	613	06 00	663	04 12
514	01 08	564	01 03	614	06 05	664	01 10
515	05 15	565	04 04	615	04 11	665	04 13
516	05 14	566	01 04	616	02 00	666	05 11
517	04 08	567	05 15	617	05 11		
518	00 03	568	04 08	618	05 15		
519	04 03	569	00 07	619	04 08	v = 5917	
520	00 01	570	04 05	620	03 02		
521	04 03	571	02 00	621	04 00		
522	01 00	572	04 00	622	00 09		
523	04 03	573	02 01	623	06 04		
524	00 02	574	04 00	624	04 05		
525	04 03	575	02 02	625	02 05		
526	00 03	576	04 00	626	06 03		
527	04 03	577	02 03	627	06 05		
528	00 04	578	04 00	628	06 08		
529	04 03	579	02 04	629	04 11		
530	00 05	580	05 15	630	06 00		
531	04 03	581	04 08	631	06 01		
532	01 07	582	03 01	632	04 05		
533	04 03	583	04 11	633	02 05		
534	01 08	584	06 00	634	06 02		
535	05 15	585	04 15	635	07 00		
536	04 08	586	01 05	636	07 00		
537	00 06	587	06 02	637	07 00		
538	05 15	588	05 15	638	07 12		
539	06 04	589	04 11	639	07 05		
540	05 15	590	02 00	640	06 00		
541	04 04	591	06 00	641	06 05		
542	00 07	592	06 05	642	04 11		
543	06 03	593	05 11	643	02 00		
544	04 14	594	04 08	644	05 11		
545	02 02	595	03 00	645	04 08		
546	07 02	596	06 04	646	01 05		
547	06 02	597	04 05	647	04 00		
548	04 14	598	01 05	648	00 04		
549	02 03	599	06 03	649	04 05		