

1983/31. FORTRAN programs for performing gravity reduction (Revision 1)

R.G. Richardson

**Abstract**

The main program calculates observed Bouguer anomalies from station position, gravity difference, and terrain correction data. Options are available for most forms of data specification. A short program performs conversions between the kiloyard and metric grids.

**INTRODUCTION**

The programs were adapted for use on the Department of Mines Perkin-Elmer 8/32 computer from ALGOL versions running on the ELLIOTT 503 and Burroughs B6700 computers at the University of Tasmania. The FORTRAN 77 versions described here may be easily transferred to other computers.

**THE PROGRAMS**

*U191V6 (Appendix 1)*

This program implements the gravity reduction method outlined in Leaman (1981) and uses the old equation for normal gravity. By selecting the appropriate control data, station positions may be in metric grid co-ordinates or latitude and longitude, heights may be in feet or metres, and the observed gravity may be in milligals or meter scale divisions. The data is terminated by a station number less than -9000.0. Input is on logical unit 4 and output is on logical unit 6.

Input data is:

- PA1, PA3, PA4, PA5 - format (I4, F12.4, F10.2, A8)
- PA1 is the survey number and has the form (for the Department of Mines) XX51 where XX is the year of the survey
  - PA3 is the number of the reference station
  - PA4 is the absolute gravity value at the reference station (milligals)
  - PA5 is the date of reference station establishment e.g. 041181
- PA6, SCONST, PA8 - format (A4, F10.5, A8)
- PA6 is the meter number e.g. W273, S308
  - SCONST is the meter scale constant in milligals per scale division
  - PA8 is the meter calibration date e.g. 030180
- PA9, PA12, PA14, PA16, PA17 - format (5I1)
- PA9 = 1 - input elevations in metres  
= 0 - input elevations in feet
  - PA12 = 1 - input units milligals  
= 0 - input units scale divisions
  - PA14 = 1 - input in metric grid co-ordinates  
= 0 - input in latitude and longitude
  - PA16 = 1 - output elevations in metres  
= 0 - output elevations in feet
  - PA17 = 1 - output in grid co-ordinates  
= 0 - output in latitude and longitude

2/16

RHO, HTCOR           - format (F6.2, F9.2)  
                      - RHO is the Bouguer density (t/m<sup>3</sup>)  
                      - HTCOR is any elevation datum change that might  
                      be required

TITLE                - format (18A4)  
                      - the survey title

For each station:

(i) input in grid co-ordinates:

A1, EAST, NORTH, ELEV, GOBS, ABC, CORR - format (F9.4, 2F10.3, F8.2,  
  F10.2, 2A4, A2, F7.2)  
- A1 is the station number in the form 8051.1234  
  or .1234  
- EAST is the east co-ordinate of the station (in  
  metres)  
- NORTH is the north co-ordinate of the station  
  (in metres)  
- ELEV is the station elevation  
- GOBS is the observed gravity difference  
- ABC is an alphanumeric string  
- CORR is any correction - e.g. terrain correction

(ii) input in latitude and longitude:

A1, LATD, LATM, LATS, LOND, LONM, LONS, ELEV, GOBS, ABC, CORR  
- format (F9.4, I3, 2F6.0, I4, 2F6.0, F8.2,  
  F10.2, 2A4, A2, F7.2)  
- A1 is the station number in the form 8051.1234  
  or .1234  
- LATD is the latitude degrees (integer)  
- LATM is the latitude minutes (real or integer)  
- LATS is the latitude seconds (may be zero if  
  LATM is real)  
- LOND is the longitude degrees (integer)  
- LONM is the longitude minutes (real or integer)  
- LONS is the longitude seconds (may be zero if  
  LONM is real)  
- ELEV is the station elevation  
- GOBS is the observed gravity difference  
- ABC is an alphanumeric string  
- CORR is any correction - e.g. terrain correction

After the last station of a data set -99999. should appear instead  
of the station number.

Appendices 2, 3 and 4 show sample inputs and outputs.

KYD2KM (Appendix 5)

This program converts co-ordinates from the kiloyard grid to the  
metric grid. Data is prepared in the format used for U191V6 with co-  
ordinates in yards instead of metres. The program converts the co-ordinates  
and produces an output suitable for U191V6. Input is on logical unit 4 and  
output is on logical unit 6.

3/15

REFERENCE

LEAMAN, D.E. 1981. Gravity survey and reduction techniques. *Geophys. Spec.Rep.Dep.Mines Tasm.* 9.

[13 July 1983]

APPENDIX 1

Program U191V6

```

$TITL  U191V6.FTN  -   GRAVITY REDUCTION PROGRAM
C USED TO CALCULATE GRAVITY REDUCTIONS GIVEN ELEVATIONS.
C COORDS(LAT & LONG OR METRIC GRID),BASE VALUES,METER READINGS
C OR OBSERVED GRAVITIES AND TERRAIN CORRECTIONS.
C RICHARDSON,1981
C
  REAL PA6
  INTEGER*2 PA1,PA17,PA9,PA10,PA12,PA13,PA14,PA15,NA,
    PA16,NL,PA91,PA141,PA121,PA161,PA171
  DOUBLE PRECISION PA4,SCONST,PA5,PA3,PA8,RHO,HTCOR
  REAL TITLE(18)
  DOUBLE PRECISION A1,A2GRID,A5GRID,A2,A3,A4,A5,A6,A7,CORR,A2T,
    A3T,A4T,ELEV,GOBS,GTHEO,FAA,BA,GBASE
  INTEGER*2 N,IA2,IA3,IA5,IA6
  REAL ABC(3),AR(6)
C
C THE PROGRAM BODY
  READ(4,100) PA1,PA3,PA4,PA5
100 FORMAT(I4,F12.4,F10.2,A8)
C PA1=SURVEY NUMBER
C PA3=REFERENCE STATION NUMBER
C PA4=REFERENCE STATION VALUE(MGALS)
C PA5=DECIMAL DATE OF BASE STATION ESTABLISHMENT
  READ(4,101) PA6,SCONST,PA8
101 FORMAT(A4,F10.5,A8)
C PA6=METER NUMBER
C SCONST=SCALE CONSTANT
C PA8=METER CALIBRATION DATE
  READ(4,102) PA9,PA12,PA14,PA16,PA17
102 FORMAT(SI1)
  PA10=1-PA9
  PA13=1-PA12
C PA9 =1 INPUT ELEVATION METRES
C =0 INPUT ELEVATION FEET
C PA12 =1 INPUT MGALS
C =0 INPUT SCALE DIVISIONS RELATIVE TO BASE STATION
C PA14 =1 INPUT GRID COORDS
C =0 INPUT LAT/LONG
C PA16 =1 OUTPUT IN METRES
C =0 OUTPUT IN FEET
C PA17 =1 OUTPUT IN GRID COORDS
C =0 OUTPUT IN LAT/LONG
  READ(4,104) RHO,HTCOR
104 FORMAT(F6.2,F9.2)
C RHO = BOUGUER DENSITY(T/M**M**M)
C HTCOR = AN ELEVATION DATUM CHANGE
  READ(4,105) TITLE
105 FORMAT(18A4)
C ADD SIMPLE VARIABLES TO COPE WITH 1-PA9 ETC. IN PRINT STATEMENT
  PA91=1-PA9
  PA141=1-PA14
  PA121=1-PA12
  PA161=1-PA16
  PA171=1-PA17
  WRITE(6,201) PA1,PA3,PA4,PA5,PA6,SCONST,PA8,PA9,PA91,
    PA14,PA141,PA12,PA121,RHO,PA16,PA161,HTCOR,
    PA17,PA171,TITLE
201 FORMAT(30X,'SURVEY'/34X,'NUMBER',15X,I7//30X,'DATUM'/

```

5/15

```

. 34X, 'REFERENCE STATION', 4X, F12. 4/34X, 'VALUE (IN MGALS)',
. 7X, F10. 2/34X, 'DATE (DECIMAL)', 8X, A8//30X, 'METER'/34X,
. 'NUMBER', 18X, A4/34X, 'SCALE CONSTANT', 5X, F12. 5/34X,
. 'CALIBRATION DATE', 6X, A8//30X, 'FIELD DATA'/34X, 'ELEVATION'/
. 38X, 'IN METRES', 9X, I3/38X, 'IN FEET', 11X, I3/34X, 'STATION',
. ' POSITIONS'/38X, 'IN GRID COORDS', 4X, I3/38X, 'IN LAT/LONG',
. 7X, I3/34X, 'OBSERVED GRAVITY'/38X, 'IN MGALS', 10X, I3/38X,
. 'IN SCALE DIVS', 5X, I3//30X, 'OUTPUT DATA'/34X, 'BOUGUER',
. ' DENSITY', 5X, F8. 2/
. 34X, 'ELEVATION'/38X, 'IN METRES', 9X, I3/38X, 'IN FEET', 11X,
. I3/34X, 'ELEVATION DATUM CHANGE', F12. 2/34X, 'STATION ',
. 'POSITIONS'/38X, 'IN GRID COORDS', 4X, I3/38X, 'IN LAT/LONG',
. 7X, I3//20X, 18A4)
N=0
PA15=0
GBASE=PA4*1. 0D-03
CALL HEADNG(PA17)
51 CONTINUE
IF (PA14 .EQ. 1) READ(4, 106) A1, A2GRID, A5GRID, ELEV, GOBS, ABC, CORR
106 FORMAT(F9. 4, 2F10. 1, F8. 2, F10. 2, 2A4, A2, F7. 2)
C A1 = STATION NUMBER
C A2GRID = EAST GRID COORD
C A5GRID = NORTH GRID COORD
C ELEV = ELEVATION
C GOBS = OBSERVED GRAVITY
C ABC = TITLE OF LESS THAN 10 CHARACTERS
C CORR = CORRECTION TO OBSERVED GRAVITY
IF (PA14 .EQ. 0) READ(4, 107) A1, A2T, A3T, A4T, A5, A6, A7, ELEV,
. GOBS, ABC, CORR
107 FORMAT(F9. 4, I3, 2F6. 0, I4, 2F6. 0, F8. 2, F10. 2, 2A4, A2, F7. 2)
C A1 = STATION NUMBER
C A2 = LATDEG
C A3 = LAT MIN - MAY BE REAL
C A4 = LAT SEC
C A5 = LONG DEG
C A6 = LONG MIN - MAY BE REAL
C A7 = LONG SEC
C ELEV = ELEVATION
C GOBS = OBSERVED GRAVITY
C ABC = TITLE
C CORR = CORRECTION TO OBSERVED GRAVITY
IF (A1 .LT. -9000. 0D00) GOTO 71
IF (A1 .LT. 1. 0D00) A1=A1+PA1
C IF THE STATION NUMBER IS LESS THAN NUMBER THEN ADD 1 TO THE STATION
C NUMBER
C IF THE STATION NUMBER IS LESS THAN 1 ADD THE SURVEY NUMBER
PA15=PA15+1
C INCREMENT THE COUNTER FO THE NUMBER OF STATIONS
GOBS=GOBS*(DBLE(FLOAT(PA12))+DBLE(FLOAT(PA13))*SCONST)
C CONVERT FROM SCALE DIVISIONS TO MGALS
ELEV=ELEV+HTCOR
C APPLY CHANGE IN ELEVATION DATUM
ELEV=ELEV*(DBLE(FLOAT(PA9))+0. 3047997D00*DBLE(FLOAT(PA10)))
C CONVERT FEET TO METRES
IF (PA14 .EQ. 0) GOTO 10
C IF PA14=1 HAVE INPUT IN GRID COORDS
CALL GEOGRF(A2GRID, A5GRID, AR)
A2T=AR(1)
A3T=AR(2)
A4T=AR(3)

```

6/15

A5=AR(4)  
A6=AR(5)  
A7=AR(6)  
GOTO 11

C

C IF IN DEGREES CONVERT DECIMAL MINUTES TO MINUTES AND SECONDS

10 CONTINUE

CALL CONVRT(A3T, A4T)

CALL CONVRT(A6, A7)

11 CONTINUE

A2=A2T

A3=A3T

A4=A4T

GOBS=(GOBS+CORR)\*1.0D-03+GBASE

A2=(A2+A3/60.0D00+A4/3600.0D00)\*0.0174532925D+00

A3=DSIN(A2)

GTHEO=978.0490D00+5.172314332D00\*A3\*A3-0.0057704891D00\*

4.0D00\*A3\*A3\*(1.0D00-A3\*A3)

FAA=0.000308772D00\*ELEV\*(1.0D00-0.001422D00\*A3\*A3)

+7.2D-11\*ELEV\*ELEV+GOBS-GTHEO

BA=-6.2831853D00\*RHO\*6.67D-06\*ELEV

BA=FAA+BA

IF (PA16 .EQ. 0) ELEV=ELEV\*3.2808399D00

C ELEVATION BACK TO FEET IF NEEDED

GOBS=GOBS-CORR\*1.0D-03

FAA=FAA-CORR\*1.0D-03

BA=BA\*1.0D03

IA2=A2T

IA3=A3T

IA5=A5

IA6=A6

IF (PA17 .EQ. 0) GOTO 20

IF (PA14 .EQ. 1) GOTO 19

C IF OUTPUT WANTED IN LAT/LONG OR INPUT ALREADY IN GRID COORDS

C BYPASS

ALATD=A2T

ALATM=A3T

ALATS=A4T

ALOND=A5

ALONM=A6

ALONS=A7

CALL GEOUTM(ALATD, ALATM, ALATS, ALOND, ALONM, ALONS, A2GRID, A5GRID)

C CONVERT TO KM GRID

A5GRID=A5GRID-5000000.0D00

C REMOVE THE LEADING SE6

19 IF (PA17 .EQ. 1) WRITE(6, 202) A1, A2GRID, A5GRID, ELEV, GOBS,

GTHEO, CORR, BA, ABC

202 FORMAT(F12.4, 2F10.0, F10.2, 2F11.5, 2F8.2, 4X, 2A4, A2)

20 IF (PA17 .EQ. 0) WRITE(6, 203) A1, IA2, IA3, A4T, IA5, IA6, A7,

ELEV, GOBS, GTHEO, CORR, BA, ABC

203 FORMAT(F12.4, 2I4, F6.1, I5, I4, F6.1, F10.2, 2F11.5, 2F8.2, 4X, 2A4, A2)

N=N+1

IF (N .LT. 55) GOTO 71

CALL HEADNG(PA17)

N=0

71 CONTINUE

IF (A1 .GT. 0.0) GOTO 51

WRITE(6, 204) PA15

204 FORMAT(/I5)

STOP

```

END
SUBROUTINE DECDEG(ANGLE, IDEG, MIN, SEC)
DOUBLE PRECISION ANGLE, SEC
INTEGER*2 IDEG, MIN
DOUBLE PRECISION DEGI, RMIN
IDEG=IFIX(SNGL(ANGLE))
DEGI=IDEG
ANGLE=60.0D00*(ANGLE-DEGI)
MIN=IFIX(SNGL(ANGLE))
RMIN=MIN
SEC=60.0D00*(ANGLE-RMIN)
RETURN
END
SUBROUTINE GEOGRF(EAST, NORTH, ANSWER)
DOUBLE PRECISION NORTH, EAST
REAL ANSWER(6)
DOUBLE PRECISION TMD1, ORTH, DEG, TMD2, CON, Q1, DOG, SIND, COSD,
TAND, TANSQ, SINSEC, C, D, DTAN, R, P, PCUBE, POR, PFIVE, P1, P2, P3, P4,
P5, GLAT, TEMPL, DLONG, DC, SLO, SLA
DOUBLE PRECISION VAL(16), Q(5)
INTEGER*2 I, IDLA, MLA, IDLO, MLO
C CONVERTS AMG GRID COORDS (IN METRES) TO LATS AND LONGS
C INPUT OF NORTH COORDINATE EXCLUDES LEADING 5 FOR USE IN TASMANIA
C E. G. 5326446.014 BECOMES 326446.014
VAL(1)=9.033D-06
VAL(2)=1.1113334878D05
VAL(3)=3.4906585D-02
VAL(4)=6.981317D-02
VAL(5)=1.04719755D-01
VAL(6)=9.008D-06
VAL(7)=1.745329252D-02
VAL(8)=0.66945418546D-02
VAL(9)=1.99840032D-08
VAL(10)=23.96162303D-20
VAL(11)=5.9928028794D-14
VAL(12)=119.76019192D-26
VAL(13)=2.9964014397D-14
VAL(14)=14.970023989D-26
VAL(15)=6.3354611409D06
VAL(16)=1.60389546D04
C
ORTH=NORTH+5.0D06
C ADD THE LEADING 5 TO THE NORTH COORDINATE
TMD1=1.0D07-ORTH
DEG=VAL(1)*TMD1
C
DO 10 I=1, 10
TMD2=VAL(2)*DEG-VAL(16)*DSIN(VAL(3)*DEG)+
16.83310D00*DSIN(VAL(4)*DEG)-0.0218D00*DSIN(VAL(5)*DEG)
CON=TMD1-0.9996D00*TMD2
IF (DABS(CON) .LT. 1.0D-03) GOTO 14
DEG=DEG+VAL(6)*CON
10 CONTINUE
GOTO 16
C
14 CONTINUE
Q1=(EAST-500000.0D00)*1.0D-06
Q(1)=Q1
DO 11 I=2, 5
Q(I)=Q(I-1)*Q1

```

```

11 CONTINUE
   DOG=VAL(7)*DEG
   SIND=DSIN(DOG)
   COSD=DCOS(DOG)
   TAND=SIND/COSD
   TANSQ=TAND*TAND
   SINSEC=0.48481368111D-05
   C=1.0D00-VAL(8)*SIND*SIND
   D=0.27777777779D01
   DTAN=D*TAND
   R=VAL(15)/C**1.5
   P=637816.0D01/C**0.5
   PCUBE=P**3
   POR=P/R
   PFIVE=PCUBE*P*P
   P1=DTAN/(VAL(9)*R*P*SINSEC)
   P2=DTAN*(5.0D00+3.0D00*TANSQ)/(VAL(10)*R*PCUBE*SINSEC)
   P3=D/(P*COSD*SINSEC*.9996D-02)
   P4=D*(POR+2.0D00*TANSQ)/(VAL(11)*PCUBE*SINSEC*COSD)
   P5=D*(5.0D00+TANSQ*(20.0D00+24.0D00*TANSQ))/(VAL(12)*
      COSD*PFIVE*SINSEC)
   GLAT=DEG-P1*Q(2)+P2*Q(4)
   TEMPL=P3*Q1-P4*Q(3)+P5*Q(5)
   DLONG=TEMPL+7.0D00
   CALL DECDEG(DLONG, IDLO, MLO, SLO)
   IDLO=IDLO+140
   CALL DECDEG(GLAT, IDLA, MLA, SLA)
   GOTO 18
16 CONTINUE
   WRITE(5,100)
100 FORMAT(' ***** GEOGRAPHICAL ERROR *****')
   STOP 9998
18 CONTINUE
   ANSWER(1)=IDLA
   ANSWER(2)=MLA
   ANSWER(3)=SLA
   ANSWER(4)=IDLO
   ANSWER(5)=MLO
   ANSWER(6)=SLO
C STORE LAT AND LONG READY TO RETURN
   RETURN
   END
   SUBROUTINE CONVRT(A,B)
   DOUBLE PRECISION A,B
   INTEGER*2 I
   A=A+(B/60.0D00)
   I=IFIX(SNGL(A))
   B=(A-DBLE(FLOAT(I)))*60.0D00
   A=I
   RETURN
   END
   SUBROUTINE HEADNG(PA17)
   INTEGER*2 PA17
   WRITE(6,100)
100 FORMAT(1H1)
   IF (PA17 .EQ. 0) WRITE(6,102)
102 FORMAT(' ST NUMBER LATITUDE LONGITUDE',
   . 6X, 'HEIGHT OBS GRAY THEO GRAY CORR' , 4X, 'BA' , 7X,
   . 'COMMENT'//)
   IF (PA17 .EQ. 1) WRITE(6,113)

```

9/15

```

113 FORMAT(3X, 'ST NUMBER      EAST', 5X, 'NORTH', 5X,
. 'HEIGHT OBS GRAY  THEO GRAY', 3X, 'CORRN', 4X, 'BA',
. 7X, 'COMMENT' /)
RETURN
END
$TITLE GEOUTM GRID CONVERSION
SUBROUTINE GEOUTM(ALATD, ALATM, ALATS, ALOND, ALONM, ALONS, EAST, YNORTH)
C BASED ON THE TAS LANDS DEPT PROGRAM UTM
C THE EQUATIONS USED ARE FROM TM PROJECTION TABLES 1944.
C THE ORIGINAL FORMULAE AGREE WITH REDFEARNS FOR THE 1ST. AND
C 2ND. TERMS BUT DIFFER IN THE 3RD. TERM. HOWEVER TO IMPROVE
C ACCURACY THE FORMULA FOR NORTHING HAS BEEN CHANGED TO AGREE
C WITH REDFEARNS IN THE 3RD. TERM (Q3)
C CONVERTS FROM GEOGRAPHIC TO UTM COORDINATES
C INPUT IS LATDEG, LATMIN, LATSEC
C      LONDEG, LONMIN, LONSEC
C OUTPUT IS EAST COORDINATE, NORTH COORDINATE (DOUBLE PRECISION, METRES)
DOUBLE PRECISION DEG, S, EAST, YNORTH, SIND, COSD, TAND, C, R, P, PC, PCC,
. P1, P2, Q1, Q2, Q3, Q4, Q5, Q6
DEG=DBLE(ALATD)+DBLE(ALATM)/60. 0D00+DBLE(ALATS)/3600. 0D00
S=111133. 34878D00*DEG-16038. 9546D00*DSIN(0. 034906585D00*DEG)+
. 16. 8331D00*DSIN(0. 0698132D00*DEG)-0. 0218D00*DSIN(0. 10472D00*DEG)
DEG=0. 01745329252D00*DEG
SIND=DSIN(DEG)
COSD=DCOS(DEG)
TAND=(SIND/COSD)**2
C=1. 0D00-0. 6694541855D-2*SIND**2
R=6335461. 141D00/C**1. 5
P=6378160. 0D00/DSQRT(C)
PC=P*COSD
PCC=PC*COSD**2
P1=(DBLE(ALONS)+DBLE(ALONM))*60. 0D00+DBLE(ALOND)*3600. 0D00
. -529200. 0D00)*1. D-4
P2=P1**2
Q1=1. D+7-0. 9996D00*S
Q2=PC*SIND*0. 117475144D-2
Q3=PCC*SIND*(4. 0D00*(P/R)**2+P/R-TAND)*0. 230099D-6
Q4=PC*0. 48461975563D-1
Q5=PCC*(P/R-TAND)*0. 18984519D-4
Q6=PCC*COSD*COSD*(5. 0D00-TAND*(18. 0D00-TAND))*0. 22311D-8
EAST=500000. 0D00+P1*(Q4+P2*(Q5+P2*Q6))
YNORTH=Q1-P2*(Q2+P2*Q3)
RETURN
END

```

10/16

APPENDIX 2

Sample data, latitude input

```

8051      8051.9900 980169.78 181280
W913      0.0940 131278
10010
  2.67
QUE RIVER MINE AREA 1980
.6001 41    35  57.4 145    41  47.5  695.4  10.53  1.47
.6002 41  35.93    145 41.73    683.7  28.08  1.48
-99999.

```

```

SURVEY
  NUMBER                8051

DATUM
  REFERENCE STATION    8051.9900
  VALUE (IN MGALS)     980169.78
  DATE (DECIMAL)       181280

METER
  NUMBER                W913
  SCALE CONSTANT       0.09400
  CALIBRATION DATE     131278

FIELD DATA
  ELEVATION
    IN METRES          1
    IN FEET            0
  STATION POSITIONS
    IN GRID COORDS    0
    IN LAT/LONG       1
  OBSERVED GRAVITY
    IN MGALS           0
    IN SCALE DIVS     1

OUTPUT DATA
  BOUGUER DENSITY      2.67
  ELEVATION
    IN METRES          1
    IN FEET            0
  ELEVATION DATUM CHANGE  0.00
  STATION POSITIONS
    IN GRID COORDS    0
    IN LAT/LONG       1

```

QUE RIVER MINE AREA 1980

ST NUMBER	LATITUDE			LONGITUDE			HEIGHT	OBS GRAY	THEO GRAY	CORRN	BA	COMMENT
8051.6001	41	35	57.4	145	41	47.5	695.40	980.17077	980.32319	1.47	-14.14	
8051.6002	41	35	55.8	145	41	43.8	683.70	980.17242	980.32315	1.48	-14.75	

2

31-11

11/16

12/16

APPENDIX 3

Sample data, AMG input and output

```

8051 8051.9900 980169.78 181280
W913 0.0940 131278
10110
2.67 0.0
QUE RIVER MINE AREA GRAVITY SURVEY DECEMBER 1980
.6001 391373. 393878. 695.4 10.53 1.47
.6002 391283. 393926. 683.7 28.08 1.48
.6003 391396. 393869. 698.5 7.10 1.44
.6004 391419. 393860. 699.2 3.32 1.44
.6005 391442. 393850. 700.6 -0.96 2.00
-99999.

```

```

SURVEY
NUMBER 8051

DATUM
REFERENCE STATION 8051.9900
VALUE (IN MGALS) 980169.78
DATE (DECIMAL) 181280

```

```

METER
NUMBER W913
SCALE CONSTANT 0.09400
CALIBRATION DATE 131278

```

```

FIELD DATA
ELEVATION
IN METRES 1
IN FEET 0
STATION POSITIONS
IN GRID COORDS 1
IN LAT/LONG 0
OBSERVED GRAVITY
IN MGALS 0
IN SCALE DIVS 1

```

```

OUTPUT DATA
BOUGUER DENSITY 2.67
ELEVATION
IN METRES 1
IN FEET 0
ELEVATION DATUM CHANGE 0.00
STATION POSITIONS
IN GRID COORDS 1
IN LAT/LONG 0

```

QUE RIVER MINE AREA GRAVITY SURVEY DECEMBER 1980

31-13

ST NUMBER	EAST	NORTH	HEIGHT	OBS GRAY	THEO GRAY	CORRN	BA	COMMENT
8051. 6001	391373.	393878.	695. 40	980. 17077	980. 32319	1. 47	-14. 14	
8051. 6002	391283.	393926.	683. 70	980. 17242	980. 32315	1. 48	-14. 75	
8051. 6003	391396.	393869.	698. 50	980. 17045	980. 32320	1. 44	-13. 89	
8051. 6004	391419.	393860.	699. 20	980. 17009	980. 32321	1. 44	-14. 12	
8051. 6005	391442.	393850.	700. 60	980. 16969	980. 32321	2. 00	-13. 69	

5

13/6

14/16

APPENDIX 4

Sample data, AMG input, latitude and longitude output

8051 8051.9900 980169.78 181280  
W913 0.0940 131278  
10110  
2.67 0.0

QUE RIVER MINE AREA GRAVITY SURVEY					DECEMBER 1980	
.6001	391373.	393878.	695.4	10.53		1.47
.6002	391283.	393926.	683.7	28.08		1.48
.6003	391396.	393869.	698.5	7.10		1.44
.6004	391419.	393860.	699.2	3.32		1.44
.6005	391442.	393850.	700.6	-0.96		2.00
-99999.						

SURVEY  
NUMBER 8051

DATUM  
REFERENCE STATION 8051.9900  
VALUE (IN MGALS) 980169.78  
DATE (DECIMAL) 181280

METER  
NUMBER W913  
SCALE CONSTANT 0.09400  
CALIBRATION DATE 131278

FIELD DATA  
ELEVATION  
IN METRES 1  
IN FEET 0  
STATION POSITIONS  
IN GRID COORDS 1  
IN LAT/LONG 0  
OBSERVED GRAVITY  
IN MGALS 0  
IN SCALE DIVS 1

OUTPUT DATA  
BOUGUER DENSITY 2.67  
ELEVATION  
IN METRES 1  
IN FEET 0  
ELEVATION DATUM CHANGE 0.00  
STATION POSITIONS  
IN GRID COORDS 0  
IN LAT/LONG 1

QUE RIVER MINE AREA GRAVITY SURVEY DECEMBER 1980

31-15

ST NUMBER	LATITUDE			LONGITUDE			HEIGHT	OBS GRAY	THEO GRAY	CORRN	BA	COMMENT
8051.6001	41	35	57.4	145	41	47.5	695.40	980.17077	980.32319	1.47	-14.14	
8051.6002	41	35	55.8	145	41	43.6	683.70	980.17242	980.32315	1.48	-14.75	
8051.6003	41	35	57.7	145	41	48.5	698.50	980.17045	980.32320	1.44	-13.89	
8051.6004	41	35	58.0	145	41	49.5	699.20	980.17009	980.32321	1.44	-14.12	
8051.6005	41	35	58.3	145	41	50.4	700.60	980.16969	980.32321	2.00	-13.69	

R/16

16/16

APPENDIX 5

Program KYD2KM

```

$TITL  KYD2KM      CONVERT FROM KILOYARD GRID TO METRIC GRID
C COORDS. ARE IN FACT IN YARDS AND METRES.
C N. B. THE METRIC COORDINATES ARE LACKING THE LEADING 5
      DOUBLE PRECISION EAST, YNORTH, SNUM, OEAST, ONORTH, OESTSQ,
      ONTHSQ, ODIFF
      DIMENSION A(20), B(10)
      EQUIVALENCE (A(1), B(1))
      DO 10 I=1, 5
      READ(4, 100) A
      WRITE(6, 100) A
100  FORMAT(20A4)
      10 CONTINUE
C COPY CONTROL INFORMATION FROM HEAD OF FILE
      15 READ(4, 200) SNUM, OEAST, ONORTH, ELEV, GOBS, B, CORR
      200 FORMAT(F9. 4, 2F10. 1, F8. 2, F10. 2, 10A1, F7. 2)
      IF (SNUM .LT. -9000. 0D00) GOTO 40
C END OF DATA IF NEGATIVE
      OESTSQ=OEAST*OEAST
      ONTHSQ=ONORTH*ONORTH
      ODIFF=OESTSQ-ONTHSQ
      EAST=0. 914664D00*OEAST-0. 012023D00*ONORTH+5. 7D-11*OEAST
           *ONORTH-8. 4D-10*ODIFF+60756. 0D00
      YNORTH=0. 012023D00*OEAST+0. 914664D00*ONORTH-1. 678D-9*OEAST
           *ONORTH-2. 85D-11*ODIFF+4587325. 0D00
      YNORTH=YNORTH-5. 0D6
      WRITE(6, 200) SNUM, EAST, YNORTH, ELEV, GOBS, B, CORR
      GOTO 15
      40 CONTINUE
      WRITE(6, 201)
      201  FORMAT(' -999999. ')
      STOP
      END

```